

MiK_TE_X Manual

Revision 1.20e (MiK_TE_X 1.20e)
December 1999

MiK_TE_X

Christian Schenk <cs@miktex.de>

Copyright © 1996–1999 Christian Schenk

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided that the entire resulting derived work is distributed under the terms of a permission notice identical to this one.

Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions, except that this permission notice may be stated in a translation approved by the Free Software Foundation.

1 What is MiKTeX?

1.1 MiKTeX Features

MiKTeX is a free TeX distribution for Windows. Its main features are:

- Native Windows implementation with support for long file names.
- On-the-fly generation of missing fonts.
- TDS (TeX directory structure) compliant.
- Open Source.
- Advanced TeX compiler features:
 - TeX can insert source file information (aka source specials) into the DVI file. This feature can improve Editor/Previewer interaction.
 - TeX can read compressed input files.
 - The input encoding can be changed via TCX tables.
- Previewer features:
 - Supports graphics (PostScript, BMP, WMF, ...)
 - Supports colored text (through color specials)
 - Supports PostScript fonts
 - Supports TrueType fonts
 - Understands HyperTeX (`html:`) specials
 - Understands source (`src:`) specials
 - Customizable magnifying glasses
- MiKTeX is network friendly:
 - integrates well into a heterogeneous TeX environment
 - supports UNC file names
 - supports multiple TEXMF directory trees
 - uses a file name database for efficient file access
 - Setup Wizard can be run unattended

The MiKTeX distribution consists of the following applications:

- TeX 3.14159: The classic TeX compiler.
- e-TeX 2.1: A feature-extended version of TeX.
- Yap 0.97: The MiKTeX DVI previewer.
- pdfTeX 0.14d: Creates PDF files from TeX documents.
- dvipdfm 0.12.6e: Converts DVI files into PDF documents.
- Omega 1.8: An enhanced version of TeX with support for 16-bit character sets.
- METAFONT 2.718: Converts font specifications into raster fonts.
- MetaPost 0.641: Converts picture specifications into PostScript commands.

- dvips 5.86: Converts DVI files into PostScript.
- MakeIndex 2.12: Composes indexes.
- BibTeX 0.99c: Composes bibliographies.
- Standard LaTeX Packages: AMS-LaTeX, Babel, PSNFSS, ...
- TeXinfo, PSutils, . . . : Lots of utilities.

1.2 How to get MiKTeX

MiKTeX Distribution

The MiKTeX distribution is archived in the CTAN¹ directory

`'systems/win32/miktex/'`.

You can use one of the following URLs to download MiKTeX:

```
ftp://ftp.dante.de/tex-archive/systems/win32/miktex/  
ftp://ftp.tex.ac.uk/tex-archive/systems/win32/miktex/  
ftp://ctan.tug.org/tex-archive/systems/win32/miktex/
```

Other Packages

Here is a list of other packages you should take into consideration:

Aladdin Ghostscript (<http://www.cs.wisc.edu/~ghost/aladdin/index.html>)

Ghostscript is an interpreter for the PostScript language. The DVI previewer Yap uses Ghostscript to display EPS graphics.

Adobe Acrobat Reader (<http://www.adobe.com/prodindex/acrobat/readstep.html>)

A PDF viewer.

WinEdt (<http://www.winedt.com>)

WinEdt is a shareware TeX editor/shell. It cooperates with MiKTeX with respect to forward and inverse DVI search (see [Section 5.2 \[Source Specials\]](#), [page 27](#)).

ActivePerl (<http://www.activestate.com>)

ActivePerl is an implementation of Perl for the Windows platform. A few MiKTeX utilities (e.g. `psmerge`) are Perl scripts. You should install Perl if you want to use these utilities.

1.3 The MiKTeX Project Page

You can visit the [MiKTeX Project Page](#) for information about new releases, patches and so on.

¹ CTAN: Comprehensive TeX Archive Network

1.4 The MiKTeX Mailing List

MiKTeX Mailing List

There is a discussion list for MiKTeX. To join this list, send an e-mail to <miktex-request@dsts.dk> which contains the word **subscribe** as the first line in the message body.

This list is archived at www.egroups.com.

1.5 Documentation

The MiKTeX Manual (which you are reading right now) concentrates on documenting MiKTeX specific features.

Other MiKTeX related documentation includes:

Frequently Asked Questions

Lists answers to frequently asked questions.

Tips & Tricks

Lists useful tips.

Shortcuts to these documents can be found in the Start Menu (see [Section 3.2 \[Start Menu\]](#), page 13).

2 What's new in MiKTeX 1.20e?

Updated Packages

- Dvipdfm 0.12.6e; now includes the utility `dvipdft` (imbed thumbnail images).
- Texinfo 4.0
- LaTeX <1999/06/01>, Babel v3.6z, Hyperref v6.67e
- AMS-LaTeX v2
- pdfTeX 0.14d
- FreeType 1.3 utilities: `getafm`, `ttf2pfb`, `ttf2pk`, `ttf2tfm`

New Features

- TeX: the TeX compiler accepts fully qualified file names with spaces, i.e. it's now possible to say something like: `'latex "C:\My Thesis\Thesis.tex"'`.
- TeX: new option `'--interaction=mode'`: sets TeX's interaction mode (one of: `batchmode`, `nonstopmode`, `scrollmode`, `errorstopmode`).
- TeX: new option `'--quiet'`: suppresses output unless there are errors (implies `'--c-style-errors'`).
- Yap: two new toolbar buttons to control color interpolation of text.
- Yap: emTeX line specials are now supported.
- TeXify: new option `'--run-viewer'`: invokes a viewer on the resulting `'pdf'`/`'dvi'` file. This option (and some Registry wizardry) makes it possible to associate `'tex'` files with a viewer, i.e. double-clicking a `'tex'` file opens the resulting `'pdf'`/`'dvi'` file.
- TeXify: new option `'--viewer-option=option'`: can be used to pass *option* to the viewer.
- TeXify: new option `'--mkidx-option=option'`: can be used to pass *option* to the index generator. Useful if one wants to specify MakeIndex style files.
- TeXify: new option `'--tex-option=option'`: can be used to pass *option* to the (La)TeX compiler.
- METAFONT: new option `'--screen'`: enables METAFONT's online display (thanks to Wolfgang Kleinschmit who supplied the patches).

Anti Features

- TtH has been removed from the MiKTeX distribution due to license problems (TtH is not free software).

3 Installing MiKTeX

3.1 Running the Setup Wizard


1. If you still have MiKTeX 1.11 installed on your computer, then you should use the uninstall option of MiKTeX 1.11.
2. Make sure that you have enough disk space. A complete MiKTeX installation consumes approximately 40MB of disk space.
3. It is highly recommended that you login as Administrator, if you're installing MiKTeX on a Windows NT computer.
4. Choose a location for the installation directory, say `c:\texmf`. This directory receives the files of the MiKTeX distribution.
5. You can cause MiKTeX to deposit newly created files (fonts, memory dumps, filename databases) in a separate directory tree. This directory tree is called the *Local TEXMF Tree*. If you decide to create such a tree, then you must choose a name for its root directory, say `c:\localtexmf`.

Benefits that a local tree provides include the following:


- Fast file search: MiKTeX assumes that only the local tree can receive new fonts and the like, i.e. MiKTeX can trust in the file name database when the remaining (non-local) trees are searched for a file.
 - You can use the local tree for your own additions (macros, fonts).
 - Easier updates: You don't have to worry about future MiKTeX updates, since the local tree will not be overwritten by the setup program.
 - You can install the MiKTeX distribution on a read-only media.
6. Decide whether you want to incorporate a preexisting TEXMF tree. For example, if you have a TeXLive CD in CDROM drive `e:`, then it is possible to include `e:\texmf` in the MiKTeX search path.
 7. Start the MiKTeX Setup Wizard (`setupwiz.exe`). You will be presented with the welcome page:




8. Click 'Next>' to go to the next page. Enter the name of the installation directory which you have chosen in step 4:




9. Click 'Next>' to go to the next page. Choose the components that want to install:




10. Click 'Next>' to go to the next page. Enter the name of the local TEXMF directory which you have chosen in step 5 or check the button 'No local TEXMF tree', if you don't need a local tree:




11. Click 'Next>' to go to the next page. You are now asked about the list of additional TEXMF root directories. Enter a semicolon-separated list of preexisting TEXMF root directories. Check the button 'No preexisting TEXMF directory trees', if you just want to use the TEXMF tree that comes with MiKTeX:



12. Click 'Next>' to go to the next page, where you can review the setup options:



13. Click 'Next>' to start the installation process. The selected components will be copied to the installation folder chosen in step 4. Eventually you will see the finish page:



14. Click 'Finish' to exit the Setup Wizard.

The Setup Wizard does not change the environmental variable `PATH`, i.e. you may have to add something like

```
set PATH=%PATH%;c:\texmf\miktex\bin
```

to your `autoexec.bat`.

3.1.1 Setup Options

Some setup options can be specified on the command-line and/or in a separate text file named `setupwiz.opt`.

You can invoke the MiKTeX Setup Wizard with the following command-line options:

- `--additional-directory-trees DIRS`
Specify additional TEXMF directories.
- `--allow-unattended-reboot`
Allow a reboot in unattended mode.

- `--dry-run` Simulate the installation process. No files will be installed. The log file will be written to the temporary directory.
- `--installation-directory DIR` Specify the installation directory.
- `--help` Show available options and exit.
- `--no-additional-directory-trees` Prevent MiKTeX from using additional directory trees.
- `--no-local-directory` Prevent MiKTeX from using a local directory.
- `--program-folder FOLDER` Specify the MiKTeX program folder.
- `--unattended` Run Setup Wizard in unattended mode. No user input is required.

Command-line options can also be specified in a text file named `setupwiz.opt`. This file must be in the same directory as `setupwiz.exe`.

3.2 Items in the Start menu

The Setup Wizard creates the following Start Menu items:

Shortcuts to documentation files

- MiKTeX | Help | Frequently Asked Questions
Opens a Windows Help file which contains answers to frequently asked questions.
- MiKTeX | Help | LaTeX2e Reference
Opens a Windows Help file which contains descriptions for many LaTeX commands.
- MiKTeX | Help | Local Guide
Opens a Windows Help file which contains the MiKTeX Manual.
- MiKTeX | Help | Release Notes
Last-minute notes.
- MiKTeX | Help | Tips and Tricks
Opens a Windows Help file which contains a list of useful tips.

Shortcuts to the configuration utility (`initexmf.exe`)

- MiKTeX | Maintenance | Create All Format Files
Creates all format files, i.e. runs `'initexmf --dump'`.
- MiKTeX | Maintenance | Create LaTeX Format File
Creates the LaTeX format, i.e. runs `'initexmf --dump=latex'`.

MiKTeX | Maintenance | Reconfigure

Creates all format files and refreshes the file name database.

MiKTeX | Maintenance | Refresh File Name Database

Refreshes the file name database.

Shortcuts to GUI-based MiKTeX applications**MiKTeX | Yap**

A shortcut to the DVI viewer.

3.3 The TEXMF Directory Hierarchy

The setup program creates a TDS-compliant directory structure. This structure is normally distributed over two physical directory trees:

1. The *installation directory* (usually ‘`c:\texmf`’) contains all files from the MiKTeX distribution.
2. The *local directory* (usually ‘`c:\localtexmf`’) receives all files that are created on-the-fly.

These directories need not be on the same drive.

It’s possible to change the locations of these directories anytime. See [Section 4.1.1 \[Defining TEXMF Root Directories\]](#), page 16, for more information.

3.3.1 Installation Directory

The installation directory (usually `c:\texmf`) is the root of a TDS-compliant directory hierarchy. If you have installed the complete distribution, then the installation directory contains the following sub-directories:

`bibtex`, `dvips`, `makeindex`, ...

These directories contain application related input files.

`doc` This directory contains all user documentation.

`fonts` This directory contains fonts in various formats.

`miktex` The `miktex` directory is reserved for MiKTeX related files:

`miktex\bin`

Contains all executable files.

`miktex\config`

Contains the global configuration file `miktex.ini` and the MiKTeX font mapping file `miktex.map`. The MiKTeX Setup Wizard installs its own log file here.

`miktex\base`

Contains the METAFONT string pool file `mf.pool`.

`miktex\fmt`
Contains TeX string pool files: `etex.pool`, `pdftex.pool`,
`omega.pool`, `tex.pool`.

`miktex\mem`
Contains the MetaPost string pool file `mp.pool`.

3.3.2 Local Directory

The local directory (usually `c:\localtexmf`) receives files that are generated on-the-fly. For example, if the TeX compiler needs a TeX Font Metric (TFM) file that is not available yet, then it creates that file (if possible) and installs it in an appropriate sub-directory of the local directory.

Typically, the Local Directory contains the following sub-directories:

fonts Contains font files that are not part of the MiKTeX distribution, but that were created on-the-fly.

`miktex\config`
This directory contains the file name database files.

3.4 Removing MiKTeX

There is no uninstall option (yet), thus you have to do it by hand if you decide to remove MiKTeX:

1. Remove the main TEXMF folder (usually `c:\texmf`) including sub folders.
2. Remove the local TEXMF folder (usually `c:\localtexmf`) including sub folders.
3. Remove Registry entries:
 1. Start `regedit`
 2. Open the key `HKEY_LOCAL_MACHINE\SOFTWARE` and delete the MiK subkey.
 3. Open the key `HKEY_CURRENT_USER\Software` and delete the MiK subkey.
4. Remove the MiKTeX item from the Windows start menu.
5. Remove the `bin` directory from the `PATH`.

4 Configuring MiKTeX

4.1 The MiKTeX Configuration Utility

`initexmf.exe` is the MiKTeX configuration utility. You can use it to

- redefine the list of TEXMF root directories
- refresh the file name database
- update standard dump files (`plain.fmt` and friends)
- define the name and location of a personal configuration file

4.1.1 Defining TEXMF Root Directories

The standard setup procedure creates two TEXMF root directories:

- `c:\texmf`: the installation directory (see [Section 3.3.1 \[Installation Directory\]](#), page 14).
- `c:\localtexmf`: the local directory (see [Section 3.3.2 \[Local Directory\]](#), page 15).

You can redefine the TEXMF root directories by using the command-line switches `--root-directories` and `--local-root`:

`--root-directories=dirlist`

This switch defines the list of TEXMF root directories. *dirlist* is a semicolon-separated list of directory path names.

`--local-root=dir`

This switch defines the local directory.

It is necessary to refresh the file name database whenever you redefine the TEXMF root directories (see [Section 4.1.2 \[Maintaining the File Name Database\]](#), page 16).

4.1.2 Maintaining the file name database

To speed up file search, MiKTeX makes use of a list of known file names. This list is called the file name database (FNDB). The FNDB is spread over several files, one for each TEXMF root directory.

The FNDB file for the first TEXMF tree is called `texmf0.fndb`. For the second tree it is called `texmf1.fndb`. And so on.

It is strongly recommended that you update the FNDB whenever files are added to or removed from one of the TEXMF trees.

You update all `fndb` files by invoking `initexmf` with the command line switch `--update-fndb`:

```
c:\> initexmf --update-fndb
```

You can update a certain FNDB file by specifying the TEXMF root. For example,

```
c:\> initexmf --update-fndb=c:\texmf
```

will update the FNDB file for the tree rooted at `c:\texmf`.

4.1.3 Maintaining the PostScript resource database

The PostScript resource database (PSres) is used by some utilities in order to locate PostScript resources (font outlines/metrics/encodings).

The database is located in the MiKTeX config directory (usually 'c:\texmf\miktex\config'). The name of the database file is 'dpres.dpr'. It is a text file, i.e. you can view it with a conventional text editor.

It is strongly recommended that you update the database whenever PostScript resources (*.pfb;*.afm;*.enc) are added to or removed from one of the TEXMF trees.

You update the database files by invoking `initexmf` with the command line switch `--mkpsres`:

```
c:\> initexmf --mkpsres
```

4.1.3.1 Incorporating External Font Directories

It is possible to add non-MiKTeX font directories to the PostScript resource database. The `--mkpsres` switch accepts as an optional argument the name of an external font directory. You can use several `--mkpsres` switches with one invocation of `initexmf`.

By specifying the command line flag `--search`, you can cause `initexmf` to automatically search your workstation for third party PostScript resource files (e.g. Acrobat Reader fonts):

```
c:\> initexmf --mkpsres --search
```

4.1.4 Making Standard Dump Files

Some programs initialize itself by reading parts of the memory from an external file. For the TeX family of programs, such a file is called a *Dump File*.

The MiKTeX configuration file has built-in rules for standard dump files.

Non-standard dump files (i.e. dump files not mentioned in this section) must be created with the ini-version of the program. For example, you would say '`initex texinfo @dump`' to produce a Texinfo dump file (`texinfo.fmt`).

You create standard dump files by invoking `initexmf` with the command line switch `--dump`. This switch takes an optional argument, which is the name of the program for which a new dump file is to be created:

```
c:\> initexmf --dump[=program]
```

If *program* is omitted, then all standard dump files will be rebuilt. Otherwise, *program* must be one of the following names:

<code>elatex</code>	This creates the dump file <code>latex.efmt</code> which is used by <code>elatex.exe</code> .
<code>etex</code>	This creates the dump file <code>plain.efmt</code> which is used by <code>etex.exe</code> .
<code>lambda</code>	This creates the dump file <code>lambda.fmt</code> which is used by <code>lambda.exe</code> .
<code>latex</code>	This creates the dump file <code>latex.fmt</code> which is used by <code>latex.exe</code> .
<code>tex</code>	This creates the dump file <code>plain.fmt</code> which is used by <code>tex.exe</code> .
<code>metafont</code>	This creates the dump file <code>plain.base</code> which is used by <code>mf.exe</code> (METAFONT).

metapost This creates the dump file `plain.mem` which is used by `mpost.exe` (MetaPost).
omega This creates the dump file `omega.fmt` which is used by `omega.exe`.
pdflatex This creates the dump file `pdflatex.fmt` which is used by `pdflatex.exe`.
pdftex This creates the dump file `pdftex.fmt` which is used by `pdftex.exe`.

4.1.4.1 Controlling which hyphenation patterns are used by LaTeX

You can control the loading of hyphenation patterns by modifying the file `language.dat` (say `'initexmf --find-tex language.dat'` to find out the absolute path).

As distributed with MiKTeX, `language.dat` has the following contents:

```
% File      : language.dat
% Purpose   : specify which hyphenation patterns to load
%             while running initex
english ushyphen.tex
%ukenglish ukhyphen.tex
german ghyph31.tex
%italian ithyph.tex
%dutch nehyph2.tex
%finnish fihyph.tex
%norwegian nohyph.tex
%french f8hyph.tex
```

Lines starting with `%` are comments. The only uncommented lines in the example are `english ushyphen.tex` and `german ghyph31.tex`. That is, only hyphenation patterns for U.S. English and German will be loaded by TeX. To load other hyphenation patterns, you have to uncomment the corresponding lines.

After modifying `language.dat`, you have to create new LaTeX dump files (see [Section 4.1.4 \[Standard Dump Files\]](#), page 17).

4.1.5 Personal Configuration File

You can cause MiKTeX to read a personal configuration file (in addition to the global one) by using the command line switch `--personal`. Usage is:

```
initexmf --personal[=filename]
```

If specified, *filename* must be the name of an existing configuration file. If *filename* is omitted, then MiKTeX will not use a personal configuration file.

Values read from *filename* will override those values that were read from the global configuration file.

For example, consider the case that you have some private LaTeX style files in your home directory (say `c:\users\me`). You could write a private configuration file (say `miktex.ini`) and place it in your home directory. The configuration file should look like this:

```
[LaTeX]
Input Dirs=.;c:\users\me//;%R\tex\latex//;%R\tex\generic//
```

Then you had to announce the configuration file this way:

```
c:\ initexmf --personal=c:\users\me\miktex.ini
```

4.2 The MiKTeX Configuration File

This section discusses the usage of MiKTeX Configuration File.

4.2.1 The Two Kinds of Configuration Files

MiKTeX configuration parameters are stored in two configuration files:

- The *global configuration file* contains site-wide configuration settings (i.e. settings shared by all MiKTeX users). The name of this file is `miktex.ini`. It is located in the directory `miktex\config` relative to the installation root directory (usually `c:\texmf`).
- The optional *personal configuration file* contains per-user configuration settings. The location of the personal configuration file can be defined with the help of `initexmf` (see [Section 4.1.5 \[Personal Configuration File\]](#), page 18).

Personal configuration settings override global settings.

4.2.2 How to specify search paths

Search paths are used by MiKTeX to find special files (such as T_EX input files) within a comprehensive directory hierarchy.

A search path is a semicolon-separated list of directory paths. This list is traversed from left to right, i.e. the first directory is searched first.

In a directory path, the following character sequences have a special meaning:

- | | |
|-----------------|---|
| <code>%R</code> | A placeholder for the list of TEXMF root directories. |
| <code>//</code> | A flag, which causes MiKTeX to search recursively. |

Example

Assuming that `c:\texmf;\myserver\texmf` is the list of TEXMF root directories, the search path `.;%R\tex\latex//;%R\tex\generic//` causes L^AT_EX to search its input files in the following locations:

1. In the current directory (`.`).
2. In the directory `c:\texmf\tex\latex` and in all directories below it.
3. In the directory `\myserver\texmf\tex\latex` and in all directories below it.
4. In the directory `c:\texmf\tex\generic` and in all directories below it
5. In the directory `\myserver\texmf\tex\generic` and in all directories below it.

Testing a new search path

You can use the configuration utility `initexmf` to test whether an input file can be found via the current search path. For example, the command

```
c:\> initexmf --find-latex-input a4.sty
```

searches for the L^AT_EX input file `a4.sty`. The full path name is printed if the file was found.

4.2.3 Contents of a MiKTeX Configuration File

A MiKTeX configuration file is divided into several named sections. Each section contains configuration settings for a specific application or feature.

4.2.3.1 [BibTeX]: BibTeX Configuration Settings

The section [BibTeX] contains BibTeX related configuration settings.

Input Dirs

Search path for BibTeX input files (both databases and style files).

min_crossrefs

Minimum number of cross-refs required for automatic `cite_list` inclusion.

4.2.3.2 [Dvips]: Dvips Configuration Settings

The section [Dvips] contains Dvips related configuration settings.

CONFIGPath

Where Dvips searches its configuration files (e.g. `config.ps`).

ENCPPath

Where Dvips searches for `.enc` files.

GraphicsPath

Where Dvips searches for `.eps` files.

MAPPath

Where Dvips searches for `.map` files.

PSPPath

Where Dvips searches for PS header files.

4.2.3.3 [Graphics]: Graphics Conversion Rules

The section [Graphics] contains graphics conversion rules. Each rule has the syntax `.fromext.toext=commandline`

fromext is the file name extension of the source file. *toext* is the file name extension of the destination file. *commandline* is the command-line which does the conversion. The command-line may include the following placeholders:

%i The name of the input file.

%o The name of the output file.

The standard MiKTeX configuration file contains the following rules:

```
.gif.bmp=giftoptnm %i | ppmtobmp -windows > %o
.pcx.bmp=pcxtoptnm %i | ppmtobmp -windows > %o
.png.bmp=pngtoptnm %i | ppmtobmp -windows > %o
.tga.bmp=tgatoptnm %i | ppmtobmp -windows > %o
.tif.bmp=tifftoptnm %i | ppmtobmp -windows > %o
.tiff.bmp=tifftoptnm %i | ppmtobmp -windows > %o
```

4.2.3.4 [Magic]: Memory Settings for TeX & Friends

The section [Magic] contains memory related configuration settings. The values are used by TeX, pdfTeX and Omega for the dynamic allocation of certain data structures.

Format-Independent Values

The following parameters can be changed at run time to extend or reduce TeX's capacity. They may have different values in INITEX and in production versions of TeX.

<code>mem_min</code>	Smallest index in TeX's internal <code>mem</code> array; must be 0 or more; must be equal to <code>mem_bot</code> in INITEX, otherwise $\leq \text{mem_bot}$.
<code>mem_max</code>	Greatest index in TeX's internal <code>mem</code> array; must be strictly less than 1073741823.
<code>buf_size</code>	Maximum number of characters simultaneously present in current lines of open files and in control sequences between <code>\csname</code> and <code>\endcsname</code> ; must not exceed 1073741823.
<code>error_line</code>	Width of context lines on terminal error messages.
<code>half_error_line</code>	Width of first lines of contexts in terminal error messages; should be between 30 and $(\text{error_line} - 15)$.
<code>max_print_line</code>	Width of longest text lines output; should be at least 60.
<code>stack_size</code>	Maximum number of simultaneous input sources.
<code>max_in_open</code>	Maximum number of input files and error insertions that can be going on simultaneously.
<code>font_max</code>	Maximum internal font number; must not exceed 5000.
<code>font_mem_size</code>	Number of words of <code>font_info</code> for all fonts.
<code>param_size</code>	Maximum number of simultaneous macro parameters.
<code>nest_size</code>	Maximum number of semantic levels simultaneously active.
<code>max_strings</code>	Maximum number of strings; must not exceed 1073741823.
<code>string_vacancies</code>	The minimum number of characters that should be available for the user's control sequences and font names, after TeX's own error messages are stored.

<code>pool_size</code>	Maximum number of characters in strings, including all error messages and help texts, and the names of all fonts and control sequences; must exceed <code>string_vacancies</code> by the total length of TeX's own strings, which is currently about 23000.
<code>save_size</code>	Space for saving values outside of current group; must be at most 1073741823.
<code>trie_size</code>	Space for hyphenation patterns; should be larger for INITEX than it is in production versions of TeX.
<code>trie_op_size</code>	Space for “opcodes” in the hyphenation patterns.

Format-Dependent Values

Like the preceding parameters, the following quantities can be changed at run time to extend or reduce TeX's capacity. But if they are changed, it is necessary to rerun the initialization program INITEX to generate new tables for the production TeX program. One can't simply make helter-skelter changes to the following constants, since certain rather complex initialization numbers are computed from them.

<code>mem_bot</code>	Smallest index in the mem array dumped by INITEX; must not be less than <code>mem_min</code> .
<code>mem_top</code>	Largest index in the mem array dumped by INITEX; must be substantially larger than 0 and not greater than <code>mem_max</code> .

4.2.3.5 [MakeIndex]: MakeIndex Configuration Settings

The section [MakeIndex] contains MakeIndex related configuration settings.

<code>INDEXSTYLE</code>	Search path for MakeIndex style files.
-------------------------	--

4.2.3.6 [MakePK]: MakePK Configuration Settings

The section [MakePK] contains configuration settings that are related to the auto-creation of packed raster fonts.

<code>DestDir</code>	The specification of a directory where newly created PK (Packed Raster Font) files are to be installed. The specification may include special character sequences which will be replaced at search-time:
<code>%m</code>	The current METAFONT mode.
<code>%d</code>	The horizontal resolution (in dots per inch).

%s The font supplier (e.g. `public`).

%t The typeface name (e.g. `cm`).

Admin note: All MiKTeX users must have permission to create files in the specified directory.

4.2.3.7 [MakeTFM]: MakeTFM Configuration Settings

DestDir Where new `.tfm` files are to be installed.

The specification may contain special character sequences which are replaced at search-time:

%s The font supplier (e.g. `public`).

%t The typeface name (e.g. `cm`).

Admin note: MiKTeX users must have permission to add files to the specified directory.

4.2.3.8 [METAFONT]: METAFONT Configuration Settings

The section `[METAFONT]` contains METAFONT related configuration settings.

Input Dirs

Search path for METAFONT input files.

4.2.3.9 [MetaPost]: MetaPost Related Configuration Settings

The section `[MetaPost]` contains MetaPost related configuration settings.

Input Dirs

Where MetaPost searches for input files.

4.2.3.10 [MiKTeX]: General Configuration Settings

The section `[MiKTeX]` contains general configuration settings and search path specifications.

General Configuration Settings

Trace This is a comma separated list of trace options:

notrace Inhibits trace output to the console.

fndb Traces the file name database.

filesearch Traces the find-file machinery.

access Traces file accesses.

<code>process</code>	Traces secondary processes.
<code>tcx</code>	Traces TCX tables.
<code>error</code>	Traces error conditions.
<code>time</code>	Traces execution time.

TraceFile

The name of the trace file.

Search Path Specifications

AFMPath	Used to locate Adobe font metric files (<code>*.afm</code>).
BASEPath	Used to locate METAFONT base files (<code>*.base</code>).
ENCPATH	Used to locate <code>*.enc</code> files.
EXEPath	Used to locate executables.
FMTPath	Used to locate T _E X dump files (<code>.fmt</code>). Also used to locate e-T _E X dump files (<code>.efmt</code>).

GraphicsPath

Used to locate graphics files (`*.eps;*.bmp;...`).

MAPPath	Used to locate font map files (<code>*.map</code>).
MEMPath	Used to locate MetaPost memory files (<code>.mem</code>).
OFMPath	Used to locate Omega font metric files (<code>*.ofm</code>).
OVFPath	Used to locate Omega virtual fonts (<code>*.ovf</code>).
PKPath	Used to locate packed font raster files (<code>*.pk</code>).
PSPPath	Used to locate PostScript header files (<code>*.enc;*.map</code>);
TCXPath	Used to locate character translation files (<code>.tcx</code>).
TFMPath	Used to locate T _E X font metric files (<code>*.tfm</code>).
TTFPath	Used to locate TrueType fonts (<code>*.ttc;*.ttf</code>).
Type1Path	Used to locate Type1 fonts (<code>*.pfa;*.pfb</code>).
VFPPath	Used to locate virtual fonts (<code>*.vf</code>).

4.2.3.11 [Omega]: Omega Configuration Settings

The section `[Omega]` contains Omega related configuration settings:

Input Dirs

The search path for Omega input files.

OCPPATH	Where Omega searches for OCP files.
----------------	-------------------------------------

4.2.3.12 [otp2ocp]: otp2ocp Configuration Settings

Input Dirs

Used by `otp2ocp` to locate OTP files (`.otp`).

4.2.3.13 [pdfTeX]: pdfTeX Configuration Settings

The section `[pdfTeX]` contains pdfTeX related configuration settings.

Input Dirs

Where pdfTeX searches for input files.

PSPath

Where pdfTeX searches for font mapping files.

4.2.3.14 [ps2pk]: ps2pk Configuration Settings

The section `[ps2pk]` contains configuration settings for the `ps2pk` utility:

PSResPath

Where `ps2pk` searches for PS resource files.

4.2.3.15 [TeX]: TeX Configuration Settings

The section `[TeX]` contains TeX-related configuration settings.

Editor

The command to be started when you press `e` in the error menu.

You can use the following placeholders:

`%f` Will be replaced by the name of the input file that caused the error.

`%h` Will be replaced by a help text.

`%l` Will be replaced by the line number.

`%m` Will be replaced by the error message.

`%vindex %t`

`%t` Will be replaced by the name of the transcript file.

For example, a suitable value for `WinEdt` would be `'winedt %f -G(1,%l,0) -S(12,+1,0)'`.

For NT Emacs, set `Editor` to `'gnulientw -F +%l %f'`.

Input Dirs

Used by TeX to locate input files.

4.2.3.16 [Yap]: Yap Configuration Settings

Input Dirs

Used by Yap to locate DVI files (`*.dvi`).

4.3 The Dvips Configuration File

As distributed with MiKTeX, Dvips is configured as follows:

- When generating fonts, Dvips uses METAFONT mode `ljfour` (HP Laserjet 4).
- Horizontal resolution is 600 dpi.
- Paper size is A4.
- Dvips does not make use of the CM & AMS PostScript fonts.

You probably have to change some of these settings for your site. To do so, open the Dvips configuration file `config.ps` with your favourite text editor.

The line starting with `M` specifies the METAFONT mode which Dvips uses for the generation of new raster fonts. Enter a suitable mode here. If you don't know the mode for your output device, then take a look at `metafont/misc/modes.mf`. This file contains an annotated list of METAFONT modes.

The line starting with `D` specifies the resolution. Enter a value that matches your printer. See the Dvips manual, for more information about configuring Dvips.

5 Non-standard T_EX Features

This chapter describes features, that were added to the MiK_TE_X implementation of Donald Knuth's T_EX.

5.1 Suppressing Screen Output

The command-line option '`--quiet`' suppresses all diagnostic messages. You will see no screen output, unless there are errors. These are shown in a "C style form" and do not stop the compilation process. For example, the input file

```
foo.tex:
\documentclass{article}
\begin{document}
What's \This?
\end{documnt}
```

would cause T_EX to print one error message, as in

```
c:\> latex --quiet foo.tex
foo.tex:3: Undefined control sequence
c:\>
```

5.2 Auto-insertion of Source Specials

What are source specials?

Source specials are pieces of information embedded in a DVI file, which make a connection between the source file location (e.g. line 100 in `foo.tex`) and the DVI location (e.g. page 2 in `foo.dvi`). Source specials can improve the Edit-T_EX-View-Edit cycle:

1. You edit your source file.
2. You compile the source file to get a DVI file.
3. You execute a special editor command to open Yap, going directly to the DVI page that corresponds to the cursor location in your source file.
4. You navigate inside the DVI file (e.g. PgUp/PgDn).
5. You double-click somewhere on the DVI view; this causes Yap to bring the editor window to the front, moving the text cursor directly to the line that corresponds to the view location.

How to insert source specials

The T_EX compiler option '`--src`' inserts source specials into the DVI file. You would say

```
c:\> latex --src foo.tex
```

to create the DVI file `foo.dvi` with embedded source specials.

5.3 Quoted File Names

The T_EX handles quoted file names. This makes it possible to specify long file names that contain spaces.

For example, to compile the input file ‘long file name.tex’, you start T_EX as follows:

```
c:\> latex "long file name"
```

This produces the DVI file ‘long file name.dvi’. The log file is named ‘long file name.log’.

You can, to some extent, use quoted file names inside the T_EX document. For example,

```
\input{"extra long file name"}
```

would cause T_EX to read the file ‘extra long file name.tex’.

Things get a little bit complicated if you want to use the LaTeX primitive ‘\include’. You have to write

```
\include{"extra\space long\space file\space name"}
```

in order to get the expected result.

5.4 TCX files: Character translations

[This section is “borrowed” from the Web2C manual].

TCX (T_EX character translation) files help T_EX support direct input of 8-bit international characters if fonts containing those characters are being used. Specifically, they map an input (keyboard) character code to the internal T_EX character code (a superset of ASCII).

Of the various proposals for handling more than one input encoding, TCX files were chosen because they follow Knuth’s original ideas for the use of the ‘xchr’ and ‘xord’ tables. He ventured that these would be changed in the WEB source in order to adjust the actual version to a given environment. It turned out, however, that recompiling the WEB sources is not as simple task as Knuth predicted; therefore, TCX files, providing the possibility of changing of the conversion tables on on-the-fly, has been implemented instead.

This approach limits the portability of T_EX documents, as some implementations do not support it (or use a different method for input-internal reencoding). It may also be problematic to determine the encoding to use for a T_EX document of unknown provenance; in the worst case, failure to do so correctly may result in subtle errors in the typeset output.

While TCX files can be used with any format, using them breaks the LaTeX ‘inputenc’ package. This is why you should either use *tcxfile* or ‘inputenc’ in LaTeX files, but never both.

Specifying TCX files:

- You can specify a TCX file to be used for a particular T_EX run by specifying the command-line option ‘-translate-file=*tcxfile*’ or (preferably) specifying it explicitly in the first line of the main document ‘%& -translate-file=*tcxfile*’.
- TCX files are searched for along the TCXPath path.
- INITEX ignores TCX files.

The MiK_T_EX distribution comes with at least two TCX files, ‘`il1-t1.tcx`’ and ‘`il2-t1.tcx`’. These support ISO Latin 1 and ISO Latin 2, respectively, with Cork-encoded fonts (a.k.a. the T1 encoding). TCX files for Czech, Polish, and Slovak are also provided.

Syntax of TCX files:

1. Line-oriented. Blank lines are ignored.
2. Whitespace is ignored except as a separator.
3. Comments start with ‘%’ and continue to the end of the line.
4. Otherwise, a line consists of one or two character codes:

$$src \ [dest]$$
5. Each character code may be specified in octal with a leading ‘0’, hexadecimal with a leading ‘0x’, or decimal otherwise. Values must be between 0 and 255, inclusive (decimal).
6. If the *dest* code is not specified, it is taken to be the same as *src*.
7. If the same *src* code is specified more than once, it is the last definition that counts.

Finally, here’s what happens: when T_EX sees an input character with code *src*, it 1) changes *src* to *dest*; and 2) makes code the *dest* “printable”, i.e., printed as-is in diagnostics and the log file instead of in ‘^^’ notation.

By default, no characters are translated, and character codes between 32 and 126 inclusive (decimal) are printable. It is not possible to make these (or any) characters unprintable.

Specifying translations for the printable ASCII characters (codes 32–127) will yield unpredictable results. Additionally you shouldn’t make the following characters printable: ^^I (TAB), ^^J (line feed), ^^M (carriage return), and ^^? (delete), since T_EX uses them in various ways.

Thus, the idea is to specify the input (keyboard) character code for *src*, and the output (font) character code for *dest*.

6 T_EXify: The MiK_T_EX Compiler Driver

`texify` is a command-line utility that simplifies the production of DVI (PDF) documents: `texify` automatically runs L^AT_EX (pdfL^AT_EX), MakeIndex and BibT_EX as many times as necessary to produce a DVI (PDF) file with sorted indices and all cross-references resolved.

To run `texify` on an input file ‘`foo.tex`’, do this:

```
c:\> texify foo.tex
```

As shown in this example, the input file names to `texify` must include any extension (‘`.tex`’, ‘`.ltx`’, etc.).

There are several command-line options you can use to control `texify` (see [Section A.12 \[texify\]](#), page 43). Here are some examples:

```
‘texify --clean foo.tex’
```

All auxiliary files will be removed, i.e. only the output ‘`foo.dvi`’ file will be left in the current directory.

```
‘texify --tex-opt=--src foo.tex’
```

Passes the option ‘`--src`’ to the T_EX compiler.

```
‘texify --run-viewer foo.tex’
```

Opens the output file ‘`foo.dvi`’ (unless there are compile errors).

```
‘texify --tex-opt=--src --viewer-opt="-1 -s\"200 foo.tex\" --run-viewer  
foo.tex’
```

Compiles ‘`foo.tex`’ with source file information (‘`--src`’) and then initiates forward DVI search to open ‘`foo.dvi`’ at the source special location ‘`200 foo.tex`’. The viewer option ‘`-1`’ activates the current viewer task (if there is already one running).

Appendix A Manual Pages

A.1 Common Compiler Options

The following command-line switches are commonly supported by all T_EX compilers.

- `--buf-size=n`
Set the internal `buf_size` to *n*. `buf_size` is the maximum number of characters simultaneously present in current lines of open files and in control sequences between `\csname` and `\endcsname`; must not exceed 1073741823.
- `--c-style-errors`
Show C/C++ style error messages. This switch implies `\scrollmode`.
- `--error-line=n`
Set the internal `error_line` to *n*. `error_line` is the width of context lines on terminal error messages.
- `--half-error-line=n`
Set the internal `half_error_line` to *n*. `half_error_line` is the width of first lines of contexts in terminal error messages; should be between 30 and (`error_line` - 15).
- `--halt-on-error`
Quit after the first error.
- `--initialize`
Initialize internal tables; these tables can be `\dumped` to a dump file.
- `--interaction=mode`
Set T_EX's interaction mode (one of: `batchmode`, `nonstopmode`, `scrollmode`, `errorstopmode`).
- `--job-name=name`
Specify the name of the job. This also sets the name of all output files.
- `--job-time=filename`
Set the time of all output files to the time of *filename*.
- `--help` Show a help screen and exit.
- `--max-in-open=n`
Set the internal `max_in_open` to *n*. `max_in_open` is the maximum number of input files and error insertions that can be going on simultaneously.
- `--max-print-line=n`
Set the internal `max-print-line` to *n*. `max-print-line` is the width of longest text lines output; should be at least 60.
- `--max-strings=n`
Set the internal `max_strings` to *n*. `max_strings` is the maximum number of strings; must not exceed 1073741823.

`--mem-bot=n`
 Set the internal `mem_bot` to *n*. `mem_bot` is the smallest index in the `code` array dumped by INITEX (INIOMEGA, INIPDFTEX); must not be less than `mem_min`.

`--mem-max=n`
 Set the internal `mem_max` to *n*. `mem_max` is the greatest index in the internal `mem` array; must be strictly less than 1073741823.

`--mem-min=n`
 Set the internal `mem_min` to *n*. `mem_min` is the smallest index in the internal `mem` array; must be 0 or more; must be equal to `mem_bot` in INITEX (INIOMEGA, INIPDFTEX), otherwise \leq `mem_bot`.

`--mem-top=n`
 Set the internal `mem_top` to *n*. `mem_top` is the largest index in the `mem` array dumped by INITEX (INIOMEGA, INIPDFTEX); must be substantially larger than 0 and not greater than `mem_max`.

`--nest-size=n`
 Set the internal `nest_size` to *n*. `nest_size` is the maximum number of semantic levels simultaneously active.

`--param-size=n`
 Set the internal `param_size` to *n*. `param_size` is the maximum number of simultaneous macro parameters.

`--pool-size=n`
 Set the internal `pool_size` to *n*. `pool_size` is the maximum number of characters in strings, including all error messages and help texts, and the names of all fonts and control sequences; must exceed `string_vacancies` by the total length of the program's own strings, which is currently about 30000.

`--quiet` Suppress all output (except errors).

`--save-size=n`
 Set the internal `save_size` to *n*. `save_size` is the amount of space for saving values outside of current group; must be at most 1073741823.

`--silent` Same as `--quiet`.

`--src-specials`
 Insert source file information into the DVI file.

`--stack-size=n`
 Set the internal `stack_size` to *n*. `stack_size` is the maximum number of simultaneous input sources.

`--string-vacancies=n`
 Set the internal `string_vacancies` to *n*. `string_vacancies` is the minimum number of characters that should be available for the user's control sequences and font names, after the program's own error messages are stored.

`--tcx=name`
`--translate-file=name`
 Causes T_EX to process the TCX table *name*.

--terminal=oem
Causes T_EX to use the current DOS codepage (e.g. cp850) for console output.

--trace=traceflags
Set trace flags.

--trie-size=n
Set the internal `trie_size` to *n*. `trie_size` is the amount of space for hyphenation patterns; should be larger for INITEX (INIOMEGA, INIPDFTEX) than it is in production versions of the program.

--trie-op-size=n
Set the internal `trie_op_size` to *n*. `trie_op_size` is the amount of space for “opcodes” in the hyphenation patterns.

--try-gz Try *file.tex.gz* if *file.tex* cannot be found.

--undump=name
Causes T_EX to read the dump file *name*.

--version
Print version information and exit.

A.2 bibtex

BibT_EX is a preprocessor for the LaT_EX document-preparation system. It handles most of the formatting decisions required to produce a reference list, outputting a `.bbl` file; with this file LaT_EX actually produces the reference list.

Synopsis

```
bibtex [option...] name
```

Reads the file ‘*name.aux*’ and outputs the file ‘*name.bbl*’.

Options

--help Shows a help screen and exits successfully.

--min-crossrefs=N
Sets the internal `min_crossrefs` parameter to *N*.

--version
Shows version information and exits successfully.

Documentation

See *BibT_EXing*, available as file ‘`btxdoc.dvi`’.

A.3 bibtex8

BibTeX8 is an enhanced version of BibTeX. Enhanced by conversion to “big” (32-bit) capacity, addition of run-time selectable capacity and 8-bit support extensions. National character set and sorting order are controlled by an external configuration file.

Synopsis

```
bibtex8 [option...] name
```

where *name* is the name of the TeX auxilliary output file to be processed by `bibtex8`. The trailing `.aux` may be omitted.

Options

-?

--help Display some brief help text and then exit.

-7

--traditional

Operate in the original 7-bit mode. A CS file is not read: only 7-bit ASCII characters are supported and sorting is strictly by ASCII code value.

`bibtex8` will not allow you to specify `--traditional` with either the `--8bit` or `--csfile` option.

-8

--8bit Force 8-bit mode. A CS file is not read. All 8-bit characters (code > 127) are treated as letters and sorting is strictly by code page value.

BibTeX will not allow you to specify `--8bit` with either the `--csfile` or `--traditional` option.

-c *file*

--csfile *file*

Read *file* as the BibTeX8 codepage and sort definition (CS) file. The CS file is used to define the 8-bit character set used by BibTeX8 and the order in which those characters should be sorted.

BibTeX8 will not allow you to specify `--csfile` with either the `--8bit` or `--traditional` option.

-d *type*

--debug *type*

Report debugging information to the BibTeX8 log file and the standard error device. The value *type* controls the type of debugging information reported. *type* can be one or more of:

all all debugging categories

csf CS file processing

io file I/O

mem	memory allocation and capacity
misc	other debugging information
search	path searching and file location

-s

--statistics Report internal statistics to the BibTeX8 log file.

-t

--trace Report execution tracing to the BibTeX8 log file.

-v

--version Report BibTeX8's version and then exit.

-B

--big Set BibTeX8's capacity to "big". The size of particular parameters will be set as follows (the default sizes are shown in brackets):

Hash_Prime	8,501	(4,253)
Hash_Size	10,000	(5,000)
Max_Cites	2,000	(750)
Max_Ent_Ints	4,000	(3,000)
Max_Ent_Strs	6,000	(3,000)
Max_Fields	30,000	(17,250)
Max_Strings	10,000	(4,000)
Pool_Size	130,000	(65,530)
Wiz_Fn_Space	6,000	(3,000)

-H

--huge Set BibTeX8's capacity to "huge". The size of particular parameters will be set as follows (the default sizes are shown in brackets):

Hash_Prime	16,319	(4,253)
Hash_Size	19,000	(5,000)
Max_Cites	5,000	(750)
Max_Ent_Ints	5,000	(3,000)
Max_Ent_Strs	10,000	(3,000)
Max_Fields	85,000	(17,250)
Max_Strings	19,000	(4,000)
Pool_Size	500,000	(65,530)
Wiz_Fn_Space	10,000	(3,000)

-W

--wolfgang Set BibTeX8's capacity to "really huge" - required for Wolfgang's PhD thesis. The size of particular parameters will be set as follows (the default sizes are shown in brackets):

Hash_Prime	30,011	(4,253)
Hash_Size	35,000	(5,000)
Max_Cites	7,500	(750)

Max_Ent_Ints	7,500	(3,000)
Max_Ent_Strs	10,000	(3,000)
Max_Fields	125,000	(17,250)
Max_Strings	30,000	(4,000)
Pool_Size	750,000	(65,530)
Wiz_Fn_Space	10,000	(3,000)

`-M n`

`--min_crossrefs n`

Set `min_crossrefs` to *n*. If an item is cross-referenced at least *n* times, it will be placed in the list of citations, even if it is not explicitly `\cited` as a reference. The default value is 2.

`--mcites n`

Allow a maximum of *n* distinct `\cites` in the `.aux` files. This number must be less than the maximum number of strings (settable with `--mstrings`).

`--mentints n`

Allow a maximum of *n* integer entries in the `.bib` databases.

`--mentstrs n`

Allow a maximum of *n* string entries in the `.bib` databases.

`--mfields n`

Allow a maximum of *n* fields in the `.bib` databases.

`--mpool n` Set the string pool to *n* bytes.

`--mstrings n`

Allow a maximum of *n* unique strings. This number must be less than the hash size and greater than the maximum number of `\cites` (settable with `--mcites`).

`--mwizfuns n`

Allow a maximum of *n* wizard functions.

Documentation

For a general description of `bibtex8`, see the text file `'00readme.txt'`.

For a description of the CS file syntax see the text file `'csfile.txt'`.

A.4 dvicopy

`dvicopy` is a utility program that allows one to take a DVI file that references composite fonts (VF) and convert it into a DVI file that does not contain such references.

Synopsis

```
dvicopy [option...] old new
```

Converts DVI file *old* into *new*.

Options

- `--help` Shows a help screen and exits successfully.
- `--mag=MAG`
 Sets magnification to *MAG*.
- `--select=range`
 Selects a range of pages to be copied.
- `--version`
 Prints version information and exits successfully.

A.5 dvipdfm

`dvipdfm` is a DVI to PDF conversion utility.

Synopsis

`dvipdfm [option...] dvifile`

Options

- `-c` Ignore color specials (for printing on B&W printers).
- `-f filename`
 Set font map file name [*t1fonts.map*].
- `-o filename`
 Set output file name [*dvifile.pdf*].
- `-l` Landscape mode.
- `-m number`
 Set additional magnification.
- `-p papersize`
 Set papersize (*letter*, *legal*, *ledger*, *tabloid*, *a4*, or *a3*) [*letter*].
- `-r resolution`
 Set resolution (in DPI) for raster fonts [600].
- `-s pages` Select page ranges (-).
- `-x dimension`
 Set horizontal offset [1.0in].
- `-y dimension`
 Set vertical offset [1.0in].
- `-e` Disable partial font embedding [default is enabled].
- `-z number`
 Set compression level (0-9) [default is 9].

- v Be verbose.
- vv Be more verbose.

All dimensions entered on the command line are “true” T_EX dimensions. Argument of `-s` lists physical page ranges separated by commas, e.g., ‘`-s 1-3,5-6`’.

Documentation

See *Dvipdfm User’s Manual* (available as file ‘`dvipdfm.dvi`’, for a complete description.

A.6 dvips

`dvips` is a program to translate a DVI file into PostScript.

Synopsis

```
dvips [options...] filename[.dvi]
```

Options

See the Dvips documentation, for a list of available options.

Documentation

For a complete description of Dvips, see *Dvips: A DVI driver*. This document is available

- as a Windows help file (`dvips.hlp`)
- as a DVI file (`dvips.dvi`)

A.7 initexmf (MiK_TE_X Configuration Utility)

`initexmf` is the MiK_TE_X Configuration Utility.

Synopsis

```
initexmf [option...]
```

Options

- `--dump` Refresh all dump files (`*.base;*.efmt;*.fmt;*.mem`).
- `--dump=program`
Refresh the dump files related to a specific program. *program* must be one of: `elatex`, `etex`, `lambda`, `latex`, `metafont`, `metapost`, `omega`, `pdflatex`, `pdftex`, `tex`.
- `--find-elatex-input FILE`
Find e-La_TE_X input file.

`--find-etex-input FILE`
Find e-TeX input file.

`--find-executable FILE`
Find a MiKTeX executable.

`--find-lambda-input FILE`
Find Lambda input file.

`--find-latex-input FILE`
Find LaTeX input file.

`--find-metafont-input FILE`
Find METAFONT input file.

`--find-metapost-input FILE`
Find MetaPost input file.

`--find-omega-input FILE`
Find Omega input file.

`--find-other-executable FILE`
Find an executable.

`--find-pdflatex-input FILE`
Find pdfLaTeX input file.

`--find-pdftex-input FILE`
Find pdfTeX input file.

`--find-tex-input FILE`
Find TeX input file.

`--list-modes`
List all known METAFONT modes.

`--local-root root`
Specify the local TEXMF root.

`--mkpsres`
Update the PostScript resource database ‘psres.dpr’. You can use this option in conjunction with `--search` (see below).

`--mkpsres=dir`
Add a new font directory to the PostScript resource database ‘psres.dpr’.

`--personal`

`-p` Do not use a personal configuration file.

`--personal=filename`

`-pfilename`
Define the location of the personal configuration file.

`--print-only`

`-n` Print what would be done. Nothing is changed.

`--quiet` Suppress screen output.

```

--reconfigure      Reconfigure MiKTeX.
--report          Create a configuration report.
--root-directories dirlist
-r dirlist        Specify the list of TEXMF root directories.
--search          Search for PS resource files (requires --mkpsres).
--update-fndb
-u               Refresh the whole file name database.
--update-fndb=root
-uroot          Refresh the file name database for a specific TEXMF root.
--verbose
-v             Print information on what is being done.
--version
-V            Print the version number and exit.

```

A.8 mp (MetaPost)

MetaPost (installed as `mp`) reads a series of pictures specified in the MetaPost programming language, and outputs corresponding PostScript code.

Synopsis

```

mp [option...] [name[.mp]] [command...]
mp [option...] "&format" [command...]

```

Options

```

--c-style-errors  Show C/C++ style error messages. This switch implies \scrollmode.
--initialize      Initializes MetaPost's internal tables so that they can be dumped.
--help           Shows a short help screen and exits successfully.
--tex=texprogram
                 Uses texprogram instead of tex when compiling text labels. This flag overrides
                 the environment variable TEX.
--version        Prints version information and exits successfully.

```

Aliases

```

inimp           Equivalent to 'mp --ini'.
mpost           Equivalent to 'mp'.
virmp           Equivalent to 'mp'.

```

Environment Variables

TEX Specifies the \TeX compiler which should be used when compiling text labels.

Documentation

For a complete description of the MetaPost language, see AT&T technical report CSTR-162, available as the file ‘`mpman.ps`’.

A.9 omega

Omega is a 16-bit enhanced version of \TeX .

Synopsis

```
omega [option...] [name[.tex]] [command...]
```

Options

Omega supports the common compiler options (see [Section A.1 \[Common Compiler Options\]](#), page 31).

Aliases

```
iniomega  Equivalent to omega --ini.
viomega   Equivalent to omega.
lambda    Equivalent to omega "&lambda".
```

Documentation

For a complete description of Omega, see the Omega manual, available as the file ‘`omega-manual.dvi`’.

A.10 pdftex

pdf \TeX is a special version of \TeX that outputs PDF.

Synopsis

```
pdftex [option...] [name[.tex]] [command...]
pdftex [option...] "&format" [command...]
```

Options

Besides the common command-line switches (see [Section A.1 \[Common Compiler Options\]](#), page 31), pdf \TeX supports these options:

```
--font-max=n
    Sets the internal font_max to n. font_max is the maximum internal font number; must not exceed 5000.
```

Aliases

`inipdftex` Equivalent to `pdftex --ini`.
`virpdftex` Equivalent to `pdftex`.
`pdflatex` Equivalent to `pdftex "&pdflatex"`.

Documentation

For a complete description of pdf \TeX , see the the pdf \TeX User Manual, available as file ‘`pdftexman.pdf`’.

A.11 `tex`

`tex` is Donald Knuth’s \TeX compiler.

Synopsis

```
tex [option...] [name[.tex]] [command...]
tex [option...] "&format" [command...]
```

Options

Besides the common command-line switches (see [Section A.1 \[Common Compiler Options\]](#), [page 31](#)), `tex` supports the following options:

`--font-max=n`
 Sets the internal `font_max` to *n*. `font_max` is the maximum internal font number; must not exceed 5000.

Aliases

`latex` Equivalent to `tex "&latex"`.
`initex` Equivalent to `tex --ini`.
`virtex` Equivalent to `tex`.

See Also

See [Section A.12 \[texify\]](#), [page 43](#), for an alternative way to invoke \TeX .

Documentation

For a complete description of \TeX , see *The \TeX book* by Donald E. Knuth.

A.12 texify

`texify` runs Texinfo or LaTeX input files through TeX (pdfTeX) in turn until all cross-references are resolved, building all indices.

Synopsis

```
texify [option]... file...
```

The directory containing each *file* is searched for included files. The suffix of *file* is used to determine its language (LaTeX or Texinfo).

Makeinfo is used to perform Texinfo macro expansion before running TeX when needed.

Options

```
-@          Use @input instead of \input; for preloaded Texinfo.
-b
--batch     No interaction.
-c
--clean     Remove all auxiliary files.
-e
--expand    Force macro expansion using makeinfo.
-I dir      Search dir for input files.
-h
--help      Display this help and exit successfully.
-l lang
--language=lang
            Specify the lang of file: latex or texinfo.
--mkidx-option=option
            Pass option to the index generator.
-p
--pdf       Use pdfTeX or pdfLaTeX for processing.
-q
--quiet     No output unless errors (implies --batch).
--run-viewer
            Run a viewer on the resulting DVI/PDF file.
-s
--silent    Same as --quiet.
-t cmd
--texinfo=cmd
            Insert cmd after @setfilename in copy of input file. Multiple values accumulate.
```

`--tex-option=option`

Pass *option* to (La)(pdf)TEX.

`-v`

`--version`

Display version information and exit successfully.

`--viewer-option=option`

Pass *option* to the viewer.

Environment Variables

The values of the BIBTEX, LATEX (or PDFLATEX), MAKEINDEX, MAKEINFO, TEX (or PDFTEX), and TEXINDEX environment variables are used to run those commands, if they are set.

Aliases

`texi2dvi` Equivalent to `texify`.

Appendix B Index

%	
%d	22
%f	25
%h	25
%l	25
%m	22, 25
%R	19
%s	22, 23
%t	23
-	
--8bit	34
--additional-directory-trees	12
--allow-unattended-reboot	12
--batch	43
--big	35
--buf-size= <i>n</i>	31
--c-style-errors	31, 40
--clean	30, 43
--csfile <i>file</i>	34
--debug <i>type</i>	34
--dry-run	12
--dump	17, 38
--dump= <i>program</i>	38
--error-line= <i>n</i>	31
--expand	43
--find-elatex-input <i>FILE</i>	38
--find-etex-input <i>FILE</i>	38
--find-executable <i>FILE</i>	39
--find-lambda-input <i>FILE</i>	39
--find-latex-input	19
--find-latex-input <i>FILE</i>	39
--find-metafont-input <i>FILE</i>	39
--find-metapost-input <i>FILE</i>	39
--find-omega-input <i>FILE</i>	39
--find-other-executable <i>FILE</i>	39
--find-pdflatex-input <i>FILE</i>	39
--find-pdftex-input <i>FILE</i>	39
--find-tex-input <i>FILE</i>	39
--font-max= <i>n</i>	41, 42
--half-error-line= <i>n</i>	31
--halt-on-error	31
--help	12, 31, 33, 34, 37, 40, 43
--huge	35
--initialize	31, 40
--installation-directory	12
--interaction= <i>mode</i>	4, 31
--job-name= <i>name</i>	31
--job-time= <i>filename</i>	31
--language= <i>lang</i>	43
--list-modes	39
--local-directory	12
--local-root	16
--local-root <i>root</i>	39
--mag= <i>MAG</i>	37
--max-in-open= <i>n</i>	31
--max-print-line= <i>n</i>	31
--max-strings= <i>n</i>	31
--mcites <i>n</i>	36
--mem-bot= <i>n</i>	31
--mem-max= <i>n</i>	32
--mem-min= <i>n</i>	32
--mem-top= <i>n</i>	32
--mentints <i>n</i>	36
--mentstrs <i>n</i>	36
--mfields <i>n</i>	36
--min-crossrefs= <i>N</i>	33
--min_crossrefs <i>n</i>	36
--mkidx-option= <i>option</i>	4, 43
--mkpsres	17, 39
--mkpsres='dir'	39
--mpool <i>n</i>	36
--mstrings <i>n</i>	36
--mwizfuns <i>n</i>	36
--nest-size= <i>n</i>	32
--no-additional-directory-trees	12
--no-local-directory	12
--param-size= <i>n</i>	32
--pdf	43
--personal	18, 39
--personal= <i>filename</i>	39
--pool-size= <i>n</i>	32
--print-only	39
--program-folder	12
--quiet	4, 27, 32, 39, 43
--reconfigure	39
--report	40
--root-directories	16
--root-directories <i>dirlist</i>	40
--run-viewer	4, 30, 43
--save-size= <i>n</i>	32
--screen	4
--search	17, 40
--select= <i>range</i>	37
--silent	32, 43
--src	27
--src-specials	32
--stack-size= <i>n</i>	32
--statistics	35
--string-vacancies= <i>n</i>	32
--tcx= <i>name</i>	32
--terminal= <i>mode</i>	32
--tex-option= <i>option</i>	4, 30, 43

C

character codes, in TCX files	29
character translation files	28
codepage	32
color interpolation	4
color specials	1
comments, in TCX files	29
compressed input files	1, 33
config.ps	20, 26
CONFIGPath	20
configuration file	19
configuration file, personal	18
configuration report, creating a	40
Cork encoding and ISO input	29
cp850	32
CTAN	2

D

decimal character codes, in TCX files	29
DestDir	22, 23
disk space, required	5
dpres.dpr	17
dump files, creating standard	17
DVI files, search path for	25
Dvips, configuring	20

E

Edit- \TeX -View-Edit cycle	27
Editor	25
Emacs	25
em \TeX	4
ENCPPath	20, 24
error messages, C-style	27, 31, 40
error messages, length of	21, 31
error_line	21, 31
execution time, tracing	24
EXEPath	24

F

FAQ, MiK \TeX	3
features, MiK \TeX	1, 27
file accesses, tracing	23
file name database, maintaining the	16
file name database, refreshing the	40
file name databases, tracing the	23
file search, tracing	23
FMTPath	24
FNDB (file name database)	16

font character code, translating	29
font directories, adding	17
font mapping files, search path for	24
font supplier	22
font_max	21, 41, 42
font_mem_size	21
format files, search path for	24
FreeType	4

G

Ghostscript	2
GIF (Graphics Interchange Format)	20
graphics, search path for	24
GraphicsPath	20, 24

H

half_error_line	21, 31
hex character codes, in TCX files	29
Hyperref	4
Hyper \TeX specials	1
hyphenation patterns, controlling loading of	18
hyphenation patterns, space for	22

I

il1-t1.tcx	29
il2-t1.tcx	29
INDEXSTYLE	22
initexmf	18
Input Dirs	20, 23, 24, 25
installation directory	5, 14, 16, 19
interaction mode, setting \TeX 's	31
international characters	28

J

job name	31
----------------	----

K

keyboard character code, translating	29
Kleinschmit, Wolfgang	4
Knuth, Donald E.	27, 42

L

<code>lambda.fmt</code>	17
<code>language.dat</code>	18
<code>LATEX</code>	44
<code>latex.efmt</code>	17
<code>latex.fmt</code>	17
<code>ljfour</code>	26
local directory	5, 14, 15, 16
local directory, defining the	16
log files, Setup Wizard	14
long file names	1, 4
long file names, quoting of	28

M

mailing list, MiKTeX	3
<code>MAKEINDEX</code>	44
<code>MAKEINFO</code>	44
<code>MAPPPath</code>	20, 24
<code>max_in_open</code>	21, 31
<code>max_print_line</code>	21, 31
<code>max_strings</code>	21, 31
Mekeindex, configuring	22
<code>mem_bot</code>	22, 31
<code>mem_max</code>	21, 32
<code>mem_min</code>	21, 32
<code>mem_top</code>	22, 32
memory allocation, dynamic	21
<code>MEMPath</code>	24
<code>METAFONT</code>	4, 23
<code>METAFONT</code> base files, search path for	24
<code>METAFONT</code> mode	22, 26
<code>MetaPost</code>	23, 40
<code>miktex.ini</code>	14, 19
<code>miktex.map</code>	14
MiKTeX Compiler Driver	30, 43
<code>min_crossrefs</code>	20, 33
<code>modes.mf</code>	26

N

<code>nest_size</code>	21, 32
network installation	1

O

<code>OCPPPath</code>	24
octal character codes, in TCX files	29
OEM mode	32
<code>OFMPPath</code>	24
Omega, configuring	24

<code>omega.fmt</code>	18
output file, setting name of	31
<code>OVFPath</code>	24

P

paper size	26
<code>param_size</code>	21, 32
<code>PATH</code>	12, 15
<code>PCX</code>	20
PDF, creating	30, 37, 41, 43
<code>PDFLATEX</code>	44
<code>pdflatex.fmt</code>	18
<code>PDFTEX</code>	44
<code>pdftex.fmt</code>	18
<code>pdfTEX</code>	4
<code>pdfTEX</code> , configuring	25
Perl	2
PK (Packed Raster Font)	22
PK files, search path for	24
<code>PKPath</code>	24
<code>plain.base</code>	17
<code>plain.efmt</code>	17
<code>plain.fmt</code>	17
<code>plain.mem</code>	17
PNG (Portable Network Graphics)	20
<code>pool_size</code>	21, 32
PostScript resource database, maintaining the ..	17
PostScript	2, 38
PostScript header files, search path for	24
printable characters, specifying	29
processes, tracing	23
Project Page, MiKTeX	2
<code>PSPPath</code>	20, 24, 25
PSres (PostScript resource database)	17
<code>PSResPath</code>	25

Q

quoted file names	28
-------------------------	----

R

read-only media, installing on	5
Registry	15
removing files from the TEXMF tree	16, 17
resolution	22, 26
root directories, defining	16

S

<code>save_size</code>	22, 32
screen output, suppressing	27, 32, 39, 43
screen output, width of	21
search paths, specifying	19
Setup Wizard	5
<code>setupwiz.opt</code>	12
source specials	1, 27
source specials, inserting	27, 32
spaces in file names	28
spaces, in file names	4
<code>stack_size</code>	21, 32
start menu, Windows	13
<code>string_vacancies</code>	21, 32

T

T1 encoding and ISO input	29
TCX (character translation)	1
TCX character translation files	28
TCX files, processing	32
TCX files, search path for	24
TCX files, syntax of	29
TCX files, tracing	24
<code>TCXPath</code>	24
<code>TCXPath</code> , search path for TCX files	28
TDS (T _E X directory structure)	1, 14
terminal mode, setting	32
TEX	41, 44
T _E X input files, search path for	25
T _E X, configuring	25
T _E XLive	5
TEXINDEX	44
Texinfo	4, 17, 43
<code>texinfo.fmt</code>	17
<code>texmf0.fndb</code>	16
<code>texmf1.fndb</code>	16
TFM (T _E X Font Metrics)	23

TFM files, search path for	24
<code>TFMPath</code>	24
TGA (TrueVision Targa)	20
thumbnails	4
TIFF (Tagged Image File Format)	20
Tips & Tricks, MiK _T _E X	3
Trace	23
<code>TraceFile</code>	24
tracing	23, 33
<code>trie_op_size</code>	22, 33
<code>trie_size</code>	22, 33
TrueType fonts, search path for	24
<code>TTFPath</code>	24
TtH	4
Type1 fonts, search path for	24
<code>Type1Path</code>	24

U

UNC (Universal Naming Code)	1
uninstalling MiK _T _E X	15

V

<code>VFPath</code>	24
virtual fonts, search path for	24

W

whitespace, in TCX files	29
Windows NT	5
WinEdt	2, 25
WMF (Windows Metafile)	1

Y

Yap	4
Yap, configuring	25

Table of Contents

1	What is MiKTeX?	1
1.1	MiKTeX Features	1
1.2	How to get MiKTeX	2
1.3	The MiKTeX Project Page	2
1.4	The MiKTeX Mailing List	3
1.5	Documentation	3
2	What's new in MiKTeX 1.20e?	4
3	Installing MiKTeX	5
3.1	Running the Setup Wizard	5
3.1.1	Setup Options	12
3.2	Items in the Start menu	13
3.3	The TEXMF Directory Hierarchy	14
3.3.1	Installation Directory	14
3.3.2	Local Directory	15
3.4	Removing MiKTeX	15
4	Configuring MiKTeX	16
4.1	The MiKTeX Configuration Utility	16
4.1.1	Defining TEXMF Root Directories	16
4.1.2	Maintaining the file name database	16
4.1.3	Maintaining the PostScript resource database	17
4.1.3.1	Incorporating External Font Directories	17
4.1.4	Making Standard Dump Files	17
4.1.4.1	Controlling which hyphenation patterns are used by LaTeX	18
4.1.5	Personal Configuration File	18
4.2	The MiKTeX Configuration File	19
4.2.1	The Two Kinds of Configuration Files	19
4.2.2	How to specify search paths	19
4.2.3	Contents of a MiKTeX Configuration File	20
4.2.3.1	[BibTeX]: BibTeX Configuration Settings	20
4.2.3.2	[Dvips]: Dvips Configuration Settings	20
4.2.3.3	[Graphics]: Graphics Conversion Rules	20
4.2.3.4	[Magic]: Memory Settings for TeX & Friends	21
4.2.3.5	[MakeIndex]: MakeIndex Configuration Settings	22

4.2.3.6	[MakePK]: MakePK Configuration Settings	22
4.2.3.7	[MakeTFM]: MakeTFM Configuration Settings	23
4.2.3.8	[METAFONT]: METAFONT Configuration Settings	23
4.2.3.9	[MetaPost]: MetaPost Related Configuration Settings	23
4.2.3.10	[MiKTeX]: General Configuration Settings	23
4.2.3.11	[Omega]: Omega Configuration Settings	24
4.2.3.12	[otp2ocp]: otp2ocp Configuration Settings	25
4.2.3.13	[pdfTeX]: pdfTeX Configuration Settings	25
4.2.3.14	[ps2pk]: ps2pk Configuration Settings	25
4.2.3.15	[TeX]: T _E X Configuration Settings	25
4.2.3.16	[Yap]: Yap Configuration Settings	25
4.3	The Dvips Configuration File	26
5	Non-standard T_EX Features	27
5.1	Suppressing Screen Output	27
5.2	Auto-insertion of Source Specials	27
5.3	Quoted File Names	28
5.4	TCX files: Character translations	28
6	T_EXify: The MiKTeX Compiler Driver	30
Appendix A	Manual Pages	31
A.1	Common Compiler Options	31
A.2	bibtex	33
A.3	bibtex8	34
A.4	dvicopy	36
A.5	dvipdfm	37
A.6	dvips	38
A.7	initexmf (MiKTeX Configuration Utility)	38
A.8	mp (MetaPost)	40
A.9	omega	41
A.10	pdftex	41
A.11	tex	42
A.12	texify	43
Appendix B	Index	45